Geospatial Modeling & Visualization

A Method Store for Advanced Survey and Modeling Technologies

GMV Geophysics GPS

Modeling I

Digital Photogrammetry

y 3D Scanning Equipment

t Data and Projects by Region

Rapidform: Basic Workflow to start a digitizing project Part 1

These tutorials will show you how to digitize archaeological features from terrestrial scan data. Hint: You can click on any image to see a larger version.

START A PROJECT

-Create a new project by clicking "File" and "New" -Import external scan points by going to "Insert" and "Import"



Fig. 5: Import Data into Rapidform

SELECT A FILE TO IMPORT

-Select the file containing scan data which you wish to import. For a list of valid file types, open the "Files of Types" dropdown menu.

Look in	Defiance MV		- 01	-	
	Name a		Infortemeter Information		
42	evention		8/31/2011 11:5	5. File folder	
week Discort	recovery		8/31/2011 11:5	5 File folder	11
	screenshots		9/5/2011 2:12 F	M File folder	
	August31 20	1 badscale.xrl	9/1/2011 11:45	AM Rapidform XOF	ε
Desktop	Default.xdl	9/13/2011 12:12		2 XDL File	XDL File
15	defiance_pts.	ks 8/31/2011 12:52 PT5 Fil			
	export_to_ca	d.dxf	9/13/2011 12:5	4 DXF File	XF File
Libranes	ref pts.xdl	9/13/2011 12:06 XDL File			XDL File DXF File XDL File DXF File
Room5_extens		ion.dxf 9/13/2011 9:20 AM ion.xdl 9/13/2011 12:00		AM DXF File	
				0 XDL File	
		east_wall.dxf	ast_wall.dxf 9/1/2011 5:49 PM		
-	Room6_south	west_interior.xdl	9/7/2011 4:45 P	M XDL File	
	Sept1_2011_	fefiance.xrl	10/14/2011 9:3	4 Rapidform XOF	C
Network.	vectors.xdl		9/13/2011 12:1	1 XDL File	100
	wrongscalebu	tdean.xpc	9/1/2011 12:40	PM XPC File	-
	41			1	<u>ت</u>
				_	
	File name:	defiance_pts.pts		•	
	Files of type:	All Supported Files		-	
	211250332811 - <u>}</u>	All Supported Files			1
	nis Data	XD Model files (".xdl, "	[w], ".w]		-
Fix Environments Data T Use Custom Setting Points Only Fig. Include Vertex Normal Fig.		RapidForm Extreme P Banidform2006 Mode	ont Cloud files (".xpc)		h Buildup Wizard
		Ascii Points files (".asc	;, *.xyz, *.txt)		Second Carly
		Rapidform Points files	(".pts)		amport Only
		STL files (".stf)	les (lics)		Cancel
Conbre P.	aint Gouds	OBJ files (".obj)			
	RATIO IVIL Y	CyberWare files (".ply) 30 Studio files (".3de)			
	average in the	VRML 1.0/97 files [".	wrl)		
		INUS Compression Fil	e files (".icf)		1. 14
		STEP files (".stp.", ste	p)		1
		Parasolid Text/Binary	files (".x_1, ".x_b)	ana mana ana 1	
		ACIS Text/Binary Part/Assembly files (".sat, ".sab, ".asat, ".asab]			
		CATIA V5 Part/Assembly files (" catpart, " catproduct)			-
		Pto/Engineer Part/Assembly files (".prt, ".prt,", ".asm, ".asm,")			
	010.0	SolidWorks files (".pr	ort * sidasmi		-
erralue	CAD Compa	AutoCAD DXF files ["	dof)		
iption		NextEngine files (".scr	ય		
		Steinbichier Nes (".ac) Breuckmann files (".br	e.* ctrl		
		Vivid files (".vvd, ".cdr	n, ".cdk)		
		100 march 7 allow 10 march 1	COLUMN TO THE T		

Fig. 6: Supported file types are listed in the import menu dropdown.

IMPORT ONLY OR MESH ON IMPORT?

Decide whether or not you want to mesh your data now. If you want to inspect your data before meshing, select "Import only". If this is the first time you're working with the dataset, "Import only" is probably a good idea.

SET THE SCAN RANGE

Set the Valid Scan Range to zero to import all the data.

	×
ing range will I	De DELETED.
read in full ran	nge data.
0	m 💌
OK	Cancel
	ing range will I om import opt read in full ran 0 0K

Fig. 7:Setting the Valid Scan Range.

CONFIRM THE SCALE AND THE UNITS

Confirm that your data is imported at the correct scale and make any necessary adjustments by setting the "Unit" value.

jize			
The object size o	imported data could be inappropri	ate.	e
If the imported s	ze and actual size are not matched	, choose proper unit	for actual size.
	Before: 36.8077747318 m		
	After: 36.8077747318 m		
L			
		OK	Cancel

Fig. 8: Input values should always be checked at the start of a project.

CHECK THE ALIGNMENT

Check the alignment of the scan data and adjust if necessary. A common adjustment is forcing **Z** to be up. Adjusting the alignment will allow you to use the "**Viewport**" buttons intuitively because the "**Top**" viewport will show your data from the top.



Fig. 9: The scan is misaligned when first imported. The front perspective shows a view from the top in this figure.

INTERACTIVE ALIGNMENT WIZARD STEP 1

Looking at the scan data from the Front perspective the model is incorrectly aligned.

Use the interactive alignment wizard to change this by going to "Tools" and choosing "Align" and "Interactive alignment".

😢 Rapidform XOR/Redesign				
File Select Edit Insert	Tools	Measure View	Add-I	ns Help
Mesh Region Group F Mesh Region Group F Free Free Front Front Right Origin	I	Scan Tools Mesh Tools Region Tools Point Cloud Tools Texture Tools Sketch Entities Sketch Tools Sketch Options Smart Dimension	* * * * * * * *	A ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓
		3D Sketch Entities 3D Sketch Tools	•	
		Body Tools		
		Align	•	St Wizard
				Interactive Alignment
				2월 Quick Fit Best Fit
				Batum Match
			1	

Fig. 10: The Interactive Alignment tool.

INTERACTIVE ALIGNMENT WIZARD STEP 2

Select and move the x, y, and z axes in the left-hand window to adjust the alignment of the scan data. Your adjustments will be reflected in the right-hand window. When you are satisfied with your changes, click the "check" button.



Fig. 11: Navigation in the Interactive Alignment tool.

CONTINUE TO GENERATING A MESH

Now that your scan data is properly imported, scaled and aligned you are ready to generate a mesh. Continue to **Generating a Mesh in Rapidform.**



Please cite this document as: Opitz, Rachel. 2012. Rapidform: Basic Workflow to start a digitizing project Part 1.CAST Technical Publications Series. Number 7396. http://gmv.cast.uark.edu/uncategorized/basic-workflow-to-start-a-digitizing-project-in-rapidform-part-1-4/. [Date accessed: 27 April 2013]. [Last Updated: 9 May 2012]. Disclaimer: All logos and trademarks remain the property of their respective owners.

Logir

Log i

© 2013 - Geospatial Modeling & Visualization